

Laser Programming Kit (LPK)

OEM Industrial Laser Modules

WORLD LEADERS IN MEASUREMENT TECHNOLOGY


Notes to the following pages.

- 1. Numerical values need you to Tab out of the box after entry. Either press the TAB key or click into another box to finally accept your value.
- Some options become unavailable as you make a selection. Either they will dim to show that they no longer apply or a message will appear to show any conflicts to prevent errors and unrealistic requests or parameters being sent to the laser.
- 3. Dynamic commands exist to allow a limited number of changes to the laser without being connected to the PC software or the interface board. Commands can be listed by sending 'H' to the laser via its serial port. The latest list is shown at the end of this document for reference.

On the Dynamic Data tab, some of the buttons have letters in brackets. These show the single letter command which will have the same effect in the laser itself when not connected as the button has on the screen. If a numeric value is needed then the laser will request it via text through the serial connection.


- 4. Pressing # will display the serial number of the unit and pressing? Will display the version and date of the firmware which is in the Laser Module.
- A laser does not need to be connected to the computer to create program/parameter files. These can be created on the GUI even without the laser board.

Tab Sections




Board Connections and Layout	P 24
Dynamic Serial Commands (summary)	P 25


Setup Tab 1 of 3




Setup Tab 2 of 3




Setup Tab 3 of 3




Operating Mode Tab 1 of 5




Operating Mode Tab 2 of 5



Operating Mode Tab 3 of 5



Operating Mode Tab 4 of 5




Operating Mode Tab 5 of 5


In addition to the primary range data, it is also possible to output additional data for each range measured.

- Signal Strength is an indication of the reflectivity of the target. Larger values represent stronger reflection signals.
- Pulse Count is a simple counter that increments with pulses emitted from the laser. This cycles round a 4096 maximum.
- Off, turns of any secondary output to leave just the primary measurement.
- Last Pulse data can also be output if the 'Pulse Used' section is set to First. If it is set to Last then this option will not be available.


12345.78m,12345<cr>




Trigger Tab 1 of 6




Trigger Tab 2 of 6




Trigger Tab 3 of 6



Trigger Tab 4 of 6



Trigger Tab 5 of 6



Trigger Tab 6 of 6

With the Trigger Filter turned on, the laser is looking at the distance measurements which come back from the target and if the value is between RTmin and RTmax (Range Trigger single window values), it is rounded to the nearest 10 cm and divided by 10. In memory the laser creates a virtual box with all of the possible values that could be generated between the two RT values. Each virtual location is stamped with the distance measurement that it represents. As the laser makes distance measurements it starts a log of how many readings are in each box. So for example if the laser makes the following 6 measurements (cm): 156, 160, 167, 164, 152, 160

Then the converted values would become: 16, 16, 17, 16, 15, 16

This would mean that for these 6 readings, the virtual box values would be:

..... 0, 0, 0, 1, 4, 1, 0, 0 Where the first 1 is in the 15's box and the 4 is the 16 box and the final 1 in the 17 box. We have to tell the laser how many values to store in the boxes, so in this case we have said that we want to store 6 values called the 'Total Store Value' which is shown as 20 on this screen shot. The value must be less than 32.

Using the above example, if the next measurement is 154, this would be converted to 15 and so the array would become:

..... 0, 0, 0, 2, 3, 1, 0, 0 the first 16 would be lost from the list as it is the oldest and the new 15 would be added to the end. The boxes will only hold the last 6 values in memory.

For the laser output to trigger there must be at least "Total Box Value" in one box. This is a value which we define to indicate yow many of the TSV values must be within the array. Setting "TBV" to 1, means that the laser will always be triggering as if




the filter were turned off. If we set "TBV" to be 3 in the above example, then we will trigger when one of the boxes gets 3 or more in it. If we set TBV to 4, it will cause a trigger in the first string, but not when the reading is replaced in the second.


To increase the efficiency further we have "Box Sum Number" which tells the laser how many boxes can be added together (next to each other) to get the TBV value that we need. So for example if we set BSN value to 3, then the software would read the array (from above) 0, 0, 0, 1, 4, 1, 0, 0 as 0, 1, 5, 6, 5, 1 etc. This is just adding the 3 boxes which are next to each other. This is effectively the same as re-defining boxes to be 30 cm wide rather than 10 cm without giving specific boundaries.

COM Port closed Ret Configured


Speed Tab 1 of 3




Speed Tab 2 of 3




Speed Tab 3 of 3




Dynamic Data Tab 1 of 4




Dynamic Data Tab 2 of 4




Dynamic Data Tab 3 of 4



Dynamic Data Tab 4 of 4



Connections to the board



Dynamic commands and their meanings: